SEEQUENT

Seequent Central for Hololens Installation Guide

Seequent Central for HoloLens is an EAP application for Microsoft HoloLens 2 devices, allowing Central geoscience data and models to be viewed and manipulated in a mixed reality HoloLens environment.

As the software is not currently of commercial release quality, installation is not available through the Microsoft Store.

This guide describes the manual installation process of the application using developer mode.

1. Installation

1.1. Use Developer Features

To install custom / unreleased software onto your device, "Use Developer Features" must be enabled.

- 1. Put on the HoloLens device and log in
- 2. From the Start Menu open Settings -> Update and Security
- 3. Select For Developers, then enable Use Developer Settings



Step 2 Update & Security



Step 3 Use developer features

1.2. Copy the application installer

The application installer must be transferred to the device before it can be installed. It's best to load this into the Downloads area on the HoloLens.

- 1. Put the HoloLens device on and log in.
- 2. Plug the device into your Windows computer. Note: The device must be logged in (Being worn) for file sharing to work.
- 3. Browse to the Internal Storage -> Downloads folder on the device
- 4. Copy the Central appx bundle into the Downloads folder

ST S ■ T This PC File Computer View				- u x
Properties Open Rename Location	network Open Settings Anage System System	ram		
E A A A DIFPC >		O Search This DC		
e of the states	• 0	/ Jencir ind Pc		
Quick access	V Folders (7)			
Desktop	# 3D Objects	Desktop	Documents	
Downloads	x 🧿			
Documents	2 Destate	-		
E Pictures		Music	Pictures	
		200	2	
	Videos			
	LE			
	V Devices and drives (2)			
· Contract Transmit	HOLOLENS-BOR4F4	Local Disk (C:)		
		336 GB free of 476 GB	3	
· International Association				
 Second Sciences 				
· HERITARY Revenue				
· NALTAGE CONTRACTOR				
· man frage direct discounted				
· NEW AND ADDRESS OF A PERSONNEL				
· representation for the second				
🖢 This PC				
3D Objects				
Desktop				
Documents				
Downloads				
HOLOLENS-BOR4F4				
Music				
Pictures				
Videos Videos				
ы Local Disk (C:)				
Interview Network				
Oleanor Sitem calastad				822 😅

Home Share View									~
Cut Copy Paste Shortcut	Copy De	k 🛋	New item • New folder	Properties	Select all Select none Invert selection				
Clipboard	Organize		New Open Select						
\rightarrow * \uparrow \Rightarrow This PC \Rightarrow HOLOLENS-BOR4	4F4 > Internal	Storage >	5 V	,0 Search Internal Stor	age				
Quick access		3D	Objects	Applic	ation Data		Cookies		
Desktop	30								
Downloads	*	Do	cuments	Downloads		Favorites			
Documents	*								
Pictures	*					-			
(1990) - Honora - I		Loc	ai settings	Music			Pictures		
				-		_			
 Symmetry of Algorithmics 		Videos		DAT FI	DAT File		LOG1 File		
				512 KB			284 KB		
College States		LO	iser.dat.LOG2 G2 File	Config	ini uration settings				
		88.0	0 KB	20 byte	Б				
A DESCRIPTION OF A DESC									
CORTAGE Records									
THE PARTY NAME.									
Thirtheast Receptors Accounts									
and the second second									
1980 magnetic from the second									
Introduction in the second									
This PC									
3D Objects									
Desktop									
Documents									
Downloads									
HOLOLENS-BOR4F4									
Music									
Pictures									
Videos									
🕼 Local Disk (C:)									



■ I 🔄 💷 🖛 I Downloads File Home Share View					- u	×
In to Quick Copy Poste Poste Poste shortcut	Move Copy to* to*	New tolder	Properties	Select all Select none Invert selection		
Cipboaro	Urganize	New	Open	Delect		
← → ∽ ↑ ^I ≪ HOLOLENS-BOR4F4	> Internal Storage > Downloads	ŭ v	, Search Downloads			
	Ce	ntral_1.0.4.2_arm64.appxb	undle deskto	p.ini		
★ Quick access	AF	PXBUNDLE File	Config 190 bot	uration settings		
Desktop	*	-4 mile	190 by	ies.		
Downloads	*					
Documents						
 Pictures 	*					
· Transient						
· International Association						
 CORTAN INCOMENT 						
· HETCHICK BAR SCHOOL						
· HERITAGE RECEIPTION RELATED						
· ····································						
· ····································						
· ···· ·······························						
🧢 This PC						
3D Objects						
Desktop						
Documents						
Downloads						
HOLOLENS-BOR4F4						
Music						
Pictures						
Videos						
💶 Local Disk (C:)						
Network						
2 Januar 1 Januar January 21 J 140						8:: 🔛

Step 4 Copy the Central appx bundle

1.3. Install the application

With the Central appx install bundle in the Downloads folder, Central for Hololens can be installed on the device.

- 1. From the Start Menu, open File Explorer
- 2. Browse to the Downloads folder
- 3. Launch the Central .appx installer bundle
- 4. Central will run once the installation has finished.



Step 1 Open File Explorer



Step 2 Browse to the Downloads folder



Step 3 Launch the installer bundle



2. Uninstall

2.1. Uninstall Central for Hololens

Central for Hololens may be uninstalled from Apps & features in Windows Settings.

- 1. Open Settings -> Apps
- 2. Find Central in the list of installed apps and select Uninstall.



Step 1 Open Settings -> Apps



Step 2 Uninstall the app